

Standard Operating Procedures Manual

City of Poquoson Fire and Rescue



City of Poquoson Fire and Rescue

830 Poquoson Ave.
Poquoson, VA 23662
757-868-3510
F757-868-3514


Safety and Health


SOP#: SH 7.00

Title: Post Incident
Decontamination

Effective Date: 12/01/2024

Revised Date:


Fire Chief's Signature


City Manager's Signature

Post Incident Decontamination

I. PURPOSE

To provide post fire decontamination procedures for personnel operating at a fire scene. This policy is designed to assist personnel in minimizing exposure to carcinogens and the byproducts of combustion.

This SOP is not all-inclusive and cannot encompass all situations that may be encountered.

II. SCOPE

This policy applies to all career and volunteer personnel operating on an emergency scene where contaminants or products of combustion are present and personnel have been exposed.

III. GENERAL

All personnel exposed to toxic/hazardous environment shall go through a decontamination process of their Personal Protective Equipment (PPE) and their person. Detailed decontamination procedures will be used upon exiting any Immediately Dangerous to Life or Health (IDLH) environment (including but not limited to a structure fire, vehicle fire, dumpster fire, outside trash fire) where smoke, byproducts of combustion, and/or debris is possible. This document

includes PPE exchange, Self-Contained Breathing Apparatus (SCBA) decontamination, and personal hygiene after the fire.

IV. Overview

A. Contamination is the exposure to chemicals (including carcinogens), radioactive or biological material on personnel or physical material (equipment, vehicles, etc.)

- 1.** Personnel and equipment should be considered 'contaminated' when they are exposed to a potentially toxic/hazardous environment.
- 2.** All members should be cognizant that an exposure to toxic/hazardous environments does not require visible smoke; inhalation and absorption of low doses, in the part per million (PPM) range or microscopic amounts, can have a negative effect.

B. Decontamination may be necessary for exposed or contaminated civilians and/or emergency responders.

C. The decontamination process described in this policy strictly refers to an immediate Gross Decontamination of personnel in full protective ensemble following exposure to products of combustion. This procedure has to be systematic and orderly to reduce exposure.

D. The Gross Decontamination process shall be utilized for all fires where Personal Protective Equipment (PPE) is worn and exposed to products of combustion. This shall include, but not be limited to, brush fires, vehicle fires, structure fires, training fires, and/or any other incident in where the combustion process occurs.

E. The marking of formal isolation or control zones may not occur at every fire incident. All personnel should be aware that isolation or control zones still exist. It is important to remember that many toxins are colorless and/or odorless gases. To limit

the amount of exposure and the subsequent required decontamination, consider apparatus placement and approach during any fire attack. Personnel can greatly reduce the amount of exposure by performing a fire attack from the upwind position, when possible, and utilizing the reach of the fire stream.

V. Gross Decontamination Setup:

- A.** Generally, gross decontamination should be set up by the first arriving suppression apparatus driver, closest to the incident where the byproducts of combustion exist.
 - 1.** Where resources are sufficient, it is beneficial to assign an additional officer/crew to oversee the decontamination process.
- B.** The gross decontamination area shall be designated by deploying the approved decontamination hose line and marking the nozzle location with a traffic cone.

VI. Decontamination Line Set Up:

- A.** The Decontamination Hose Line(s) shall include an in-line pressure regulator with a garden style hose and nozzle. This garden hose setup is preferred as it will provide a flushing with sufficient flow but lower water pressure, which eliminates the possibility of embedding particulates (toxins) further into the fabric. It is also easier to control water flow and direction while performing the gross decontamination process.

VII. Gross Decontamination Process:

- A.** Personnel assigned to the decontamination process shall wear personal protective equipment to reduce their exposure to carcinogens and products of combustion. At a minimum, personnel should wear EMS gloves, a HEPA mask or other appropriate respiratory protection, and splash protection for their eyes.

B. All fire personnel that were exposed to products of combustion shall perform gross decontamination prior to entering rehabilitation or leaving the scene. After exiting the IDLH, it is recommended that crews remain on-air when possible, and report directly to the designated Decontamination Hose Line(s).

1. NOTE: Those members with the lowest air supply should be decontaminated first and as a rule, personnel will remain on air until the gross decontamination is complete.

2. Maintaining crew integrity, the crew shall assist each other in rinsing off debris and products of combustion in a systematic and thorough manner from the collar-line down, being mindful of higher potential collection points such as under arms and between the legs.

3. Personnel shall also use caution to not saturate the inner lining of the protective ensemble. The goal is to keep the PPE operationally dry on the interior, but rinsed as clean as possible on the exterior. Soft bristled scrub brushes and department approved soap/cleaners may be used to facilitate the cleaning process.

C. After rinsing the exterior portion of the PPE, personnel may go off-air and begin to doff their PPE. Depending on the extent and length of the fire, all PPE, other than bunker pants and fire boots, shall be left in a prepared 'Drop Zone.' If a formal rehabilitation area is not established due to a quicker knock-down and/or demobilization, a 'Drop Zone' would not necessarily be needed.

1. The 'Drop Zone' shall be located in the warm zone and shall be remote and downwind of the rehab area due to off-gassing.

D. Personnel should then move towards the cold zone and use department approved wipes for a gross cleaning of their head,

neck, face, hands, and other exposed areas as deemed necessary.

- 1. Personnel must resist the urge to consume food or liquids until the gross decontamination process is completed and they have entered the rehabilitation area.**

VIII. Reporting to Rehab:

- A. Once in rehab, personnel shall lower their bunker pants to allow for rapid cooling and increase the distance between off gassing contaminated gear and their respiratory system and skin.**

IX. Reporting for Re-Assignment:

- A. If a crew is returned to an assignment in the ‘Hot Zone’ they are to repeat the gross decontamination procedure before returning to rehab or leaving the scene.**

X. Demobilization:

- A. Command will release units in a staggered manner to allow units to get back to the station and begin their personal decontamination process while maintaining an “in-service “unit.**

- B. To keep the cab of the apparatus as clean as possible and to avoid transferring toxins and harmful products back to the fire station, it is extremely important to perform gross decontamination prior to leaving the incident scene.**

- C. Once released by command and prior to leaving the scene, it is recommended that all PPE be bagged at the scene using department approved bags and transported back to the station in the rear of the truck. It is recommended that personnel have duty boots or shoes on the apparatus to change into prior to leaving the scene ****DO NOT PLACE CONTAMINATED GEAR IN THE CAB OF APPARATUS******

D. Decontamination of the helmet will follow the same objective as all PPE for gross decontamination. When cleaning the helmet, it is acceptable to carefully wash the exterior to remove any heavy particulates or debris. However, when cleaning the interior, DO NOT saturate any fabric, including the liners, with water.

XI. Personal Protective Equipment Exchange:

A. Personnel determined by the Incident Commander (IC) and/or the Incident Safety Officer (ISO) to have been exposed to products of combustion due to IDLH source proximity shall have their gear bagged prior to leaving the scene.

1. These exposed PPE components shall be bagged and returned to the station for cleaning by Extractor/Washer before being placed back into circulation

B. Immediately upon returning to the station the crew's second set of gear shall be readied and placed into service

XII. Post Fire Decontamination at the Fire Station:

A. It is highly recommended that all personnel exposed to the products of combustion, or any potentially harmful toxins, complete a full personal decontamination as soon as possible after the exposure. **(Remember to have staff stagger their personal decon process, ie. Having one crew shower while the other crew gets apparatus back in service.)**

1. "Shower within the Hour" shall be a priority.

2. Showering shall be accomplished with the goal of reducing the absorption rate of toxins into the body.

a. Soaps that contain alcohol should not be used because they open the pores and increase the absorption rate of the skin.

B. Officers are responsible for verifying the readiness of the crew and the unit is back in service.

C. All personnel shall ensure their assigned apparatus has a clean cab. The potential for secondary exposures during routine apparatus use is high and must be limited. To aid in reducing secondary exposures, apparatus cabs shall be cleaned and decontaminated at a minimum on a weekly basis utilizing department approved cleaners; more often may be necessary depending on call volume.

XIII. Post Fire – At the Scene: Fire Investigators:

A. The fire Investigator's duties often place them in a "post fire", chemical laden, hazardous environment. Protection is just as vital and important with this position. They must adhere to respiratory and personal protective requirements to protect against exposure to possible contaminants. It is strongly recommended that all investigators wear SCBA or respirator masks to protect their airway. Once the investigation of any fire is completed, the Fire Investigator should undergo the same gross decontamination process noted above.

B. Personal decontamination should also be performed at the nearest fire station to the incident. The goal is to prevent any transfer of contaminants from the fire scene to their homes and/or vehicles.